

# Replacing FoxIt™ Reader with Adobe Reader® for Viewpoint™

Application Version: 7.5

August 19, 2026

© 2022 Conduent, Inc. All rights reserved. Conduent and Conduent Agile Star are trademarks of Conduent, Inc. and/or its subsidiaries in the United States and/or other countries.

Other company trademarks are also acknowledged.

Document Version: 7.5 (March 2022).

## Document Conventions

| Convention                                                                        | Explanation                                                                                                                                                                   |
|-----------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Bold</b>                                                                       | For file names, commands, fields, menus, options, and window names.                                                                                                           |
| Courier New                                                                       | Commands as you should type them.                                                                                                                                             |
| Lucida Console                                                                    | Example output generated by the system.                                                                                                                                       |
| <i>Italics</i>                                                                    | For configuration variables, including variable portions of file names and URLs. Also indicates a document name.                                                              |
| Note / Blue Callout                                                               | The Blue Callout text indicates information that is of special interest or importance, an idea that could be useful or additional information about a product or a feature.   |
|  | The Caution icon along with the text indicates actions that can lead to problems in system operation or configuration settings if the instructions are not followed properly. |

## Document Revision History

This section tracks the initial creation of the document after each major version thereafter.

| Ver: | Date           | Description     | Reviewed / Approved By |
|------|----------------|-----------------|------------------------|
| 1.0  | March 25, 2022 | Initial Version | Viewpoint Team         |

# Table of Contents

- 1. Purpose..... 1-1
- 2. Viewpoint Classic Review..... 2-2
- 3. Viewpoint Processing..... 3-3
  - 3.1. Installation..... 3-3
  - 3.2. Verification / Usage..... 3-3

# 1. Purpose

The purpose of this document is to guide existing Viewpoint clients through the process of migrating from FoxIt™ Reader to Adobe Reader®. Viewpoint can use FoxIt™ Reader in two ways:

- As a 3<sup>rd</sup> party PDF viewer in Viewpoint Classic Review
- As a means of rendering PDF images to TIFF in Viewpoint Processing

## 2. Viewpoint Classic Review

Replacing FoxIt™ reader with Adobe Reader® DC is only a matter of installing Adobe Reader® DC to the machine which clients use to access Viewpoint (Citrix, Terminal Server, or standalone EXE) and then ensuring the Windows file associations are configured so that PDFs are opened with Adobe Reader® DC. No Viewpoint configuration is required. Viewpoint Classic Review does not require that FoxIt™ Reader be uninstalled. Download Adobe Reader® DC from Adobe's website.

### 3. Viewpoint Processing

Viewpoint is capable of using 3<sup>rd</sup> party tools such as FoxIt™ Reader and Adobe Reader® DC to render PDFs to TIFFs.

#### 3.1. Installation


To configure Viewpoint PMC / Workers to use Adobe Reader® DC perform the following steps – you will need sufficient rights to install software on Viewpoint Worker and Viewpoint PMC computers.

1. Install Adobe Reader® DC on each Viewpoint Worker and Viewpoint PMC computer. Download Adobe Reader® DC from Adobe's website.
2. You may choose to uninstall FoxIt™ Reader at this time, but it is not required that FoxIt™ Reader be uninstalled.

#### 3.2. Verification / Usage

To use Adobe Reader® DC to render PDFs to TIFF follow these steps.

1. Log into the Viewpoint PMC application, navigate to the Process tab.



2. Locate a Document whose native file is a PDF file.

| Original Extension | File ID Description            |
|--------------------|--------------------------------|
| pdf                |                                |
| PDF                | Adobe Portable Document For... |
| PDF                | Adobe Portable Document For... |
| PDF                | Adobe Portable Document For... |
| PDF                | Adobe Portable Document For... |
| PDF                | Adobe Portable Document For... |
| PDF                | Adobe Portable Document For... |

3. Right-click a Document and select **File ID | FileID Details...** from the right-click menu. The File Identity Details dialog will appear.
4. Locate the Create TIFF edit box at the bottom right. Populate the text box with the appropriate command line parameters:

For Adobe Reader® DC and Informatik 3.00:

```
"C:\Program Files\Adobe\Acrobat DC\Acrobat\Acrobat.exe" /N /T "{0}"
"Informatik Image Driver 3.00 (UM)"
```

For FoxIt™ Reader and Informatik 3.00:

```
"C:\Program Files (x86)\Foxit Software\Foxit Reader\FoxitReader.exe" /t
"{0}" "Informatik Image Driver 3.00 (UM)"
```



5. Click OK to save your changes to the PDF File Identity
6. Perform the Create TIFF Process on the Document. The Document's TIFF file will be populated with a TIFF created by using your selected command line settings.